Internal Rocket Terminal Emulator

Internal Rocket Terminal Emulator FAQs

Contents

Internal Rocket Terminal Emulator

FAQ #1: How to log on to the Internal Rocket Terminal Emulator

Click on the RTE icon on your desktop.

Log in with your DOE Network/LAN ID and Password

Click on TN3270 USS.

Internal Rocket Terminal Emulator


```
LU=EPTW1747  DIVISION OF INSTRUCTIONAL AND INFORMATION TECHNOLOGY    USSDOET

NYCDOE - DIIT NATIVE SERVICES                CITYNET SERVICES
-------------------------------              ------------------
ATS    - ATS PRODUCTION                      CSC      - CSC
P      - CICS PRODUCTION
CQ     - CICS QA
C      - CICS TEST
DR     - CICS TRAINING
ITOM   - IBM OUTPUT MANAGER
I      - IDMS PRODUCTION


TSOEP  - TSO CPUB



FOR ASSISTANCE, INCLUDING EIS PASSWORD RESETS,CALL THE SUPPORT CENTER
AT (718) 935-5100. FOR PASSPORT HELP CALL (718) 349-5783.
TO REFRESH THE SCREEN HIT CLEAR THEN ENTER.
FOR TSO ENTER SERVICE FOLLOWED BY A BLANK AND THEN USERID.
                        Service Desired ===>
```

Log into your Mainframe Application as you normally would.

FAQ #2: When Backspace Button on keyboard does not work in deleting characters.

Click on the three lines on the top left. That will drop down the active Sessions.

Then click on **the pencil**. See the next screenshot.

Click on Keyboard then Options and check box "**Operate 3270 Function Backspace as a Destructive Backspace**" then click **Save.**

Internal Rocket Terminal Emulator

FAQ #3: To set up your keyboard escape key.

Click on the **three lines on the top left**. That will drop down the active Sessions.

Then click on the **pencil**. See the next screenshot.

Internal Rocket Terminal Emulator

Click on Keyboard.

Click the **Action Type** and choose > 3270 Function, press the **ESC** button as shown below, and for **Actions** choose > Attn. Then click **Save**.

Internal Rocket Terminal Emulator

FAQ #4: How to change the Screen color.

Click on the three lines on the top left. That will drop down the active Sessions.

Then click on the pencil. See the next screenshot.

Internal Rocket Terminal Emulator

Click on Colors, you will see **Standard Colors** and **Extended Colors**. There you can adjust the colors.

FAQ #5: Cursor (Steady / Blinking / Show Vertical / Outline active).

Click on the three lines on the top left. That will drop down the active Sessions. Then click on the pencil. See the next screenshot.

Internal Rocket Terminal Emulator

Click on **Cursor** and check your preference.

FAQ #6: FTP - File Transfer Protocol.

TSO/ISPF PRIMARY OPTIONS MENU

6 = COMMAND

Internal Rocket Terminal Emulator

Click on the ICON IND$FILE.

Click on Refresh:

Internal Rocket Terminal Emulator

You will then see a list of your library files. Chose the file to Receive or Send.